


## Use UNIS S/W on SQL Server

UNIS software is using Microsoft Access Database(MDB) as a default however, if you want to use a SQL server, refer the SQL Script that we provide in the UNIS setup folder. After you create Database, you can set up the ODBC.

Run SetODBC.exe file on the CD



**MS SQL Server ODBC Configuration**

This program will help you create an ODBC data source that you can use to connect to SQL Server.

What name do you want to use to refer to the data source?

Name:

Which SQL Server do you want to connect to?

Server:

Port number:

Default database:

**Name:**

It means Data Source, so please type "UNIS"

**Server:**

The IP address of SQL Server

**Port number:**

The port of SQL Server, the basic port of SQL server is 1433

If you have changed the port before, you have to use the port number.

**Default database:**

Type the basic Database name

[OK] Press OK button to finish the setup

To run the modified configuration, you need to reboot your PC or restart UNIS program.

To start service program Control Panel >> Admin >> Server

Stop running UDBServerService and UNIS\_Server, and restart those two program.